

Generating Code and Running Programs

COMS W4115


Prof. Stephen A. Edwards

Spring 2002

Columbia University

Department of Computer Science

A Long K's Journey into Byte[†]



[†]Apologies to O'Neill

Compiler Frontends and Backends

The front end focuses on *analysis*:

- lexical analysis

- parsing

- static semantic checking

- AST generation

The back end focuses on *synthesis*:

- Translation of the AST into intermediate code


- optimization

- assembly code generation

Portable Compilers


Building a compiler a large undertaking; most try to leverage it by making it portable.

Instead of



Portable Compilers

Use a common intermediate representation.



Intermediate Representations/Formats

Stack-Based IR: Java Bytecode

```
int gcd(int a, int b) {    # javap -c Gcd
    while (a != b) {
        if (a > b)
            a -= b;
        else
            b -= a;
    }
    return a;
}

Method int gcd(int, int)
0  goto 19
3  iload_1           // Push a
4  iload_2           // Push b
5  if_icmple 15     // if a <= b goto 15
8  iload_1           // Push a
9  iload_2           // Push b
10 isub              // a - b
11 istore_1          // Store new a
12 goto 19
15 iload_2           // Push b
16 iload_1           // Push a
17 isub              // b - a
18 istore_2          // Store new b
19 iload_1           // Push a
20 iload_2           // Push b
21 if_icmpne 3       // if a != b goto 3
24 iload_1           // Push a
25 ireturn            // Return a
```

Stack-Based IRs

Advantages:

- Trivial translation of expressions

- Trivial interpreters

- No problems with exhausting registers

- Often compact

Disadvantages:

- Semantic gap between stack operations and modern register machines

- Hard to see what communicates with what

- Difficult representation for optimization

Register-Based IR: Mach SUIF

```
int gcd(int a, int b) {    gcd:  
    while (a != b) {        gcd._gcdTmp0:  
        if (a > b)            sne    $vr1.s32 <- gcd.a,gcd.b  
                                seq    $vr0.s32 <- $vr1.s32,0  
                                btrue $vr0.s32,gcd._gcdTmp1 //if !(a != b) goto Tmp1  
        a -= b;  
    }  
    else                    sl     $vr3.s32 <- gcd.b,gcd.a  
        b -= a;                seq    $vr2.s32 <- $vr3.s32,0  
    }                            btrue $vr2.s32,gcd._gcdTmp4 //if !(a < b) goto Tmp4  
    return a;  
}  
  
gcd._gcdTmp1:  
    mrk   2, 4 // Line number 4  
    sub   $vr4.s32 <- gcd.a,gcd.b  
    mov   gcd._gcdTmp2 <- $vr4.s32  
    mov   gcd.a <- gcd._gcdTmp2 // a = a - b  
    jmp   gcd._gcdTmp5  
gcd._gcdTmp4:  
    mrk   2, 6  
    sub   $vr5.s32 <- gcd.b,gcd.a  
    mov   gcd._gcdTmp3 <- $vr5.s32  
    mov   gcd.b <- gcd._gcdTmp3 // b = b - a  
gcd._gcdTmp5:  
    jmp   gcd._gcdTmp0  
  
gcd._gcdTmp0:
```

Register-Based IRs

Most common type of IR

Advantages:

Better representation for register machines

Dataflow is usually clear

Disadvantages:

Slightly harder to synthesize from code

Less compact

More complicated to interpret

Introduction to Optimization

Optimization

```
int gcd(int a, int b) {  
    while (a != b) {  
        if (a < b) b -= a;  
        else a -= b;  
    }  
    return a;  
}
```

First version: GCC on SPARC

Second version: GCC -O7

```
gcd: save %sp, -112, %sp  
      st  %i0, [%fp+68]  
      st  %i1, [%fp+72]  
.LL2: ld   [%fp+68], %i1  
      ld   [%fp+72], %i0  
      cmp  %i1, %i0  
      bne .LL4  
      nop  
      b   .LL3  
      nop  
.LL4: ld   [%fp+68], %i1  
      ld   [%fp+72], %i0  
      cmp  %i1, %i0  
      bge .LL5  
      nop  
      ld   [%fp+72], %i0  
      ld   [%fp+68], %i1  
      sub  %i0, %i1, %i0  
      st   %i0, [%fp+72]  
      b   .LL2  
      nop  
.LL5: ld   [%fp+68], %i0  
      ld   [%fp+72], %i1  
      sub  %i0, %i1, %i0  
      st   %i0, [%fp+68]  
      b   .LL2  
      nop  
.LL3: ld   [%fp+68], %i0  
      ret  
      restore  
gcd: cmp  %o0, %o1  
      be   .LL8  
      nop  
.LL9: bge,a .LL2  
      sub  %o0, %o1, %o0  
      sub  %o1, %o0, %o1  
.LL2: cmp  %o0, %o1  
      bne .LL9  
      nop  
.LL8: retl  
      nop
```

Typical Optimizations

Folding constant expressions

$$1+3 \rightarrow 4$$

Removing dead code

`if (0) { ... } → nothing`

Moving variables from memory to registers

```
ld    [%fp+68], %i1  
sub  %i0, %i1, %i0  → sub    %o1, %o0, %o1  
st    %i0, [%fp+72]
```

Removing unnecessary data movement

Filling branch delay slots (Pipelined RISC processors)

Common subexpression elimination;

Machine-Dependent vs. -Independent Optimization

No matter what the machine is, folding constants and eliminating dead code is always a good idea.

```
a = c + 5 + 3;  
if (0 + 3) {  
    b = c + 8;  
}  
→ b = a = c + 8;
```

However, many optimizations are processor-specific:

Register allocation depends on how many registers the machine has

Not all processors have branch delay slots to fill

Each processor's pipeline is a little different

Basic Blocks

```
int gcd(int a, int b) {  
    while (a != b) {  
        if (a < b) b -= a;  
        else a -= b;  
    }  
    return a;  
}
```

lower
→

```
A: sne t, a, b  
bz E, t  
slt t, a, b  
bnz B, t  
sub b, b, a  
jmp C  
B: sub a, a, b  
C: jmp A  
E: ret a
```

split
→

```
A: sne t, a, b  
bz E, t  
slt t, a, b  
bnz B, t  
sub b, b, a  
jmp C  
B: sub a, a, b  
C: jmp A  
E: ret a
```

The statements in a basic block all run if the first one does.


Starts with a statement following a conditional branch or is a branch target.

Usually ends with a control-transfer statement.

Control-Flow Graphs

A CFG illustrates the flow of control among basic blocks.

```
A: sne t, a, b  
    bz E, t  
  
    slt t, a, b  
    bnz B, t  
  
    sub b, b, a  
    jmp C  
  
B: sub a, a, b  
  
C: jmp A  
  
E: ret a
```



Assembly Code and Assemblers

Assembly Code

Most compilers produce assembly code: easier to debug than binary files.

```
! gcd on the SPARC
gcd:
    cmp    %o0, %o1      Comment
    be     .LL8            Operand (a register)
    nop
.LL9:   Label
    ble,a .LL2            Conditional branch to a label
    sub    %o1, %o0, %o1
    sub    %o0, %o1, %o0
.LL2:
    cmp    %o0, %o1
    bne   .LL9
    nop
.LL8:
    retl
    nop                  No operation
```

Role of an Assembler

Translate opcodes + operand into byte codes

Address	Instruction code	
	gcd:	
0000 80A20009	cmp	%o0, %o1
0004 02800008	be	.LL8
0008 01000000	nop	
	.LL9:	
000C 24800003	ble,a	.LL2
0010 92224008	sub	%o1, %o0, %o1
0014 90220009	sub	%o0, %o1, %o0
	.LL2:	
0018 80A20009	cmp	%o0, %o1
001C 12BFFFFC	bne	.LL9
0020 01000000	nop	
	.LL8:	
0024 81C3E008	retl	
0028 01000000	nop	

Encoding Example

```
sub    %o1, %o0, %o1
```

Encoding of “SUB” on the SPARC:

10	rd	000100	rs1	0	reserved	rs2
31	29	24	18	13	12	4

$$rd = \%o1 = 01001$$

$$rs1 = \%o1 = 01001$$

$$rs2 = \%o0 = 00100$$

10 01001 000100 01001 0 00000000 01000

1001 0010 0010 0010 0100 0000 0000 1000

= 0x92228004

Role of an Assembler

Transforming symbolic addresses to concrete ones.

Example: Calculating PC-relative branch offsets.

LL2 is 3 words away

000c 24800003	ble,a .LL2
0010 92224008	sub %o1, %o0, %o1
0014 90220009	sub %o0, %o1, %o0
.LL2:	
0018 80A20009	cmp %o0, %o1

Role of an Assembler

Most assemblers are “two-pass” because they can’t calculate everything in a single pass through the code.

Don't know offset of LL2



```
000c 24800003    ble,a .LL2
0010 92224008    sub    %o1, %o0, %o1
0014 90220009    sub    %o0, %o1, %o0

.LL2:
0018 80A20009    cmp    %o0, %o1
001c 12BFFFFC    bne    .LL9 ← Know offset of LL9
```

Role of an Assembler

Constant data needs to be aligned.

```
char a[] = "Hello";
int b[3] = { 5, 6, 7 };

.a:
0000 48656C6C .asciz "Hello"      ! zero-terminated ASCII
6F00

.b:
0006 0000 .global b
            .align 4
            .type   b,#object
            .size   b,12

0008 00000005 .uaword 5
000c 00000006 .uaword 6
0010 00000007 .uaword 7
```

Assembler directives

Bytes added to ensure alignment

Role of an Assembler

The MIPS has pseudoinstructions:

“Load the immediate value 0x12345abc into register 14:”

```
li $14, 0x12345abc
```

expands to

```
lui $14, 0x1234  
ori $14, 0x5abc
```

“Load the upper 16 bits, then OR in the lower 16”

MIPS instructions have 16-bit immediate values at most

RISC philosophy: small instructions for common case

Optimization: Register Allocation

Optimization: Register Allocation

Where to put temporary results? Our compiler will just put them on the stack; a typical default.

```
int bar(int g, int h, int i, int j, int k, int l)
{
    int a, b, c, d, e, f;
    a = foo(g);
    b = foo(h);
    c = foo(i);
    d = foo(j);
    e = foo(k);
    f = foo(l);
    return a + (b + (c + (d + (e + f))));
```

Quick Review of the x86 Architecture

Eight “general-purpose” 32-bit registers:

eax ebx ecx edx ebp esi edi esp

esp is the stack pointer

ebp is the base (frame) pointer

addl %eax, %edx eax + edx → edx

Base-pointer-relative addressing:

movl 20(%ebp), %eax Load word at ebp+20 into eax

Unoptimized GCC on the x86

```
movl 24(%ebp),%eax    % Get k
pushl %eax             % Push argument
call foo                % e = foo(k);
addl $4,%esp            % Make room for e
movl %eax,%eax          % Does nothing
movl %eax,-20(%ebp)     % Save return value on stack
```

```
movl 28(%ebp),%eax    % Get l
pushl %eax             % Push argument
call foo                % f = foo(l);
addl $4,%esp            % Make room for f
movl %eax,%eax          % Does nothing
movl %eax,-24(%ebp)     % Save return value on stack
```

```
movl -20(%ebp),%eax    % Get f
movl -24(%ebp),%edx    % Get e
addl %edx,%eax          % e + f
movl %eax,%edx          % Accumulate in edx
addl -16(%ebp),%edx     % d + (e+f)
movl %edx,%eax          % Accumulate in edx
```

Optimized GCC on the x86

```
movl 20(%ebp),%edx    % Get j
pushl %edx             % Push argument
call foo                % d = foo(j);
movl %eax,%esi          % save d in esi

movl 24(%ebp),%edx    % Get k
pushl %edx             % Push argument
call foo                % e = foo(k);
movl %eax,%ebx          % save e in ebx

movl 28(%ebp),%edx    % Get l
pushl %edx             % Push argument
call foo                % f = foo(l);

addl %ebx,%eax          % e + f
addl %esi,%eax          % d + (e+f)
```

Unoptimized vs. Optimized

```
movl 24(%ebp),%eax  
pushl %eax  
call foo  
addl $4,%esp  
movl %eax,%eax  
movl %eax,-20(%ebp)
```

```
movl 28(%ebp),%eax  
pushl %eax  
call foo  
addl $4,%esp  
movl %eax,%eax  
movl %eax,-24(%ebp)
```

```
movl -20(%ebp),%eax  
movl -24(%ebp),%edx  
addl %edx,%eax  
movl %eax,%edx  
addl -16(%ebp),%edx  
movl %edx,%eax
```

```
movl 20(%ebp),%edx  
pushl %edx  
call foo  
movl %eax,%esi
```


```
movl 24(%ebp),%edx  
pushl %edx  
call foo  
movl %eax,%ebx
```

```
movl 28(%ebp),%edx  
pushl %edx  
call foo
```

```
addl %ebx,%eax  
addl %esi,%eax
```

Separate Compilation and Linking

Separate Compilation



Linking

Goal of the linker is to combine the disparate pieces of the program into a coherent whole.

file1.c:

```
#include <stdio.h>    #include <stdio.h>
char a[] = "Hello";  extern char a[];
extern void bar();
int main() {
    bar();
}
void baz(char *s) { }
    printf("%s", s);
}
```

file2.c:


```
static char b[6];
void bar() {
    strcpy(b, a);
    baz(b);
}
```

libc.a:

```
int
printf(char *s, ...)
{
    /* ... */
}
char *
strcpy(char *d, char
{
    /* ... */
}
```



Linking



Object Files

Relocatable: Many need to be pasted together. Final in-memory address of code not known when program is compiled

Object files contain

- imported symbols (unresolved “external” symbols)

- relocation information (what needs to change)

- exported symbols (what other files may refer to)

Object Files

file1.c:

```
#include <stdio.h>
char a[] = "Hello";
extern void bar();

int main() {
    bar();
}

void baz(char *s) {
    printf("%s", s);
}
```

The diagram illustrates the symbol flow between two C files, file1.c and file2.c. In file1.c, the variable `a` and the function `bar()` are labeled as **exported symbols**. In file2.c, the variable `a` and the function `bar()` are labeled as **imported symbols**. Arrows show the flow of these symbols from their definitions in file1.c to their uses in file2.c, and from their uses back to their definitions.

Object Files

file1.c:

```
#include <stdio.h>
char a[] = "Hello";
extern void bar();
```

```
int main() {
    bar();
}
```

```
void baz(char *s) {
    printf("%s", s);
}
```

objdump -x file1.o

Sections:

Idx	Name	Size	VMA	LMA	Offset	Algn
0	.text	038	0	0	034	2**2
1	.data	008	0	0	070	2**3
2	.bss	000	0	0	078	2**0
3	.rodata	008	0	0	078	2**3

SYMBOL TABLE:

0000 g O	.data	006	a
0000 g F	.text	014	main
0000	*UND*	000	bar
0014 g F	.text	024	baz
0000	*UND*	000	printf

RELOCATION RECORDS FOR [.text]:

OFFSET	TYPE	VALUE
0004	R_SPARC_WDISP30	bar
001c	R_SPARC_HI22	.rodata
0020	R_SPARC_LO10	.rodata
0028	R_SPARC_WDISP30	printf

Object Files

```
file1.c:                                # objdump -d file1.o
                                         0000 <main>:
#include <stdio.h>          0: 9d e3 bf 90 save %sp, -112, %sp
char a[] = "Hello";        4: 40 00 00 00 call 4 <main+0x4>
                           4: R_SPARC_WDISP30 bar
extern void bar();         8: 01 00 00 00 nop
                           c: 81 c7 e0 08 ret
                           10: 81 e8 00 00 restore

int main() {
    bar();
}
void baz(char *s) {
    printf("%s", s);
}

# objdump -d file1.o
0000 <main>:
0: 9d e3 bf 90 save %sp, -112, %sp
4: 40 00 00 00 call 4 <main+0x4>
                           4: R_SPARC_WDISP30 bar
8: 01 00 00 00 nop
c: 81 c7 e0 08 ret
10: 81 e8 00 00 restore

0014 <baz>:
14: 9d e3 bf 90 save %sp, -112, %sp
18: f0 27 a0 44 st %i0, [%fp + 0x44]
1c: 11 00 00 00 sethi %hi(0), %o0
                           1c: R_SPARC_HI22 .rodata
20: 90 12 20 00 mov %o0, %o0
                           20: R_SPARC_LO10 .rodata
24: d2 07 a0 44 ld [%fp + 0x44], %o1
28: 40 00 00 00 call 28 <baz+0x14>
                           28: R_SPARC_WDISP30 printf
2c: 01 00 00 00 nop
30: 81 c7 e0 08 ret
34: 81 e8 00 00 restore
```

Linking

Combine object files

Relocate each function's code

Resolve previously unresolved symbols

Before and After Linking

```
int main() {
    bar();
}
```

```
void baz(char *s) {
    printf("%s", s);
}
```

```
0000 <main>:
0: 9d e3 bf 90 save %sp, -112, %sp
4: 40 00 00 00 call 4 <main+0x4>
  4: R_SPARC_WDISP30 bar
8: 01 00 00 00 nop
c: 81 c7 e0 08 ret
10: 81 e8 00 00 restore
```

```
0014 <baz>:
14: 9d e3 bf 90 save %sp, -112, %sp
18: f0 27 a0 44 st %i0, [ %fp + 0x44 ]
1c: 11 00 00 00 sethi %hi(0), %o0
  1c: R_SPARC_HI22 .rodata ← unresolved symbol
20: 90 12 20 00 mov %o0, %o0
  20: R_SPARC_LO10 .rodata
24: d2 07 a0 44 ld [ %fp + 0x44 ], %o1
28: 40 00 00 00 call 28 <baz+0x14>
  28: R_SPARC_WDISP30 printf
2c: 01 00 00 00 nop
30: 81 c7 e0 08 ret
34: 81 e8 00 00 restore
```

Code starting address changed

```
105f8 <main>:
105f8: 9d e3 bf 90 save %sp, -112, %sp
105fc: 40 00 00 0d call 10630 <bar>
10600: 01 00 00 00 nop
10604: 81 c7 e0 08 ret
10608: 81 e8 00 00 restore

1060c <baz>:
1060c: 9d e3 bf 90 save %sp, -112, %sp
10610: f0 27 a0 44 st %i0, [ %fp + 0x44 ]
10614: 11 00 00 41 sethi %hi(0x10400), %o0
10618: 90 12 23 00 or %o0, 0x300, %o0
1061c: d2 07 a0 44 ld [ %fp + 0x44 ], %o1
10620: 40 00 40 62 call 207a8
10624: 01 00 00 00 nop
10628: 81 c7 e0 08 ret
1062c: 81 e8 00 00 restore
```

Linking Resolves Symbols

file1.c:

```
#include <stdio.h>
char a[] = "Hello";
extern void bar();

int main() {
    bar();
}

void baz(char *s) {
    printf("%s", s);
}
```

file2.c:

```
#include <stdio.h>
extern char a[];

static char b[6];

void bar() {
    strcpy(b, a);
    baz(b);
}
```

```
105f8 <main>:
105f8: 9d e3 bf 90 save %sp, -112, %sp
105fc: 40 00 00 0d call 10630 <bar>
10600: 01 00 00 00 nop
10604: 81 c7 e0 08 ret
10608: 81 e8 00 00 restore

1060c <baz>:
1060c: 9d e3 bf 90 save %sp, -112, %sp
10610: f0 27 a0 44 st %i0, [ %fp + 0x44 ]
10614: 11 00 00 41 sethi %hi(0x10400), %o0
10618: 90 12 23 00 or %o0, 0x300, %o0 ! "%s"
1061c: d2 07 a0 44 ld [ %fp + 0x44 ], %o1
10620: 40 00 40 62 call 207a8 ! printf
10624: 01 00 00 00 nop
10628: 81 c7 e0 08 ret
1062c: 81 e8 00 00 restore


10630 <bar>:
10630: 9d e3 bf 90 save %sp, -112, %sp
10634: 11 00 00 82 sethi %hi(0x20800), %o0
10638: 90 12 20 a8 or %o0, 0xa8, %o0 ! 208a8 <b>
1063c: 13 00 00 81 sethi %hi(0x20400), %o1
10640: 92 12 63 18 or %o1, 0x318, %o1 ! 20718 <a>
10644: 40 00 40 4d call 20778 ! strcpy
10648: 01 00 00 00 nop
1064c: 11 00 00 82 sethi %hi(0x20800), %o0
10650: 90 12 20 a8 or %o0, 0xa8, %o0 ! 208a8 <b>
10654: 7f ff ff ee call 1060c <baz>
10658: 01 00 00 00 nop
1065c: 81 c7 e0 08 ret
10660: 81 e8 00 00 restore
10664: 81 c3 e0 08 retl
10668: ae 03 c0 17 add %o7, %17, %17
```

Shared Libraries and Dynamic Linking

Shared Libraries and Dynamic Linking

The 1980s GUI/WIMP revolution required many large libraries (the Athena widgets, Motif, etc.)


Under a *static linking* model, each executable using a library gets a copy of that library's code.



Shared Libraries and Dynamic Linking

Wasteful: running many GUI programs at once fills memory with **nearly identical** copies of each library.


Something had to be done: another level of indirection.



Shared Libraries: First Attempt

Most code makes assumptions about its location.

First solution (early Unix System V R3) required each shared library to be located at a unique address:



Shared Libraries: First Attempt

Obvious disadvantage: must ensure each new shared library located at a new address.

Works fine if there are only a few libraries; tended to discourage their use.

Shared Libraries

Problem fundamentally is that each program may need to see different libraries **each at a different address**.



Position-Independent Code

Solution: Require the code for libraries to be position-independent. **Make it so they can run anywhere in memory.**

As always, add another level of indirection:

- All branching is PC-relative

- All data must be addressed relative to a base register.

- All branching to and from this code must go through a jump table.

Position-Independent Code for bar()

Normal unlinked code

```
save %sp, -112, %sp
sethi %hi(0), %o0
    R_SPARC_HI22 .bss
mov %o0, %o0
    R_SPARC_LO10 .bss
sethi %hi(0), %o1
    R_SPARC_HI22 a
mov %o1, %o1
    R_SPARC_LO10 a
call 14
    R_SPARC_WDISP30 strcpy
nop
sethi %hi(0), %o0
    R_SPARC_HI22 .bss
mov %o0, %o0
    R_SPARC_LO10 .bss
call 24
    R_SPARC_WDISP30 baz
nop
ret
restore
```

gcc -fPIC -shared

```
save %sp, -112, %sp
sethi %hi(0x10000), %l7
call 8e0 ! add PC to %l7
add %l7, 0x198, %l7
ld [ %l7 + 0x20 ], %o0
ld [ %l7 + 0x24 ], %o1
```

call 10a24 ! strcpy

nop
ld [%l7 + 0x20], %o0

call 10a3c ! baz

nop
ret
restore

Actually just a stub

call 10a24 ! strcpy

call is PC-relative